

RDS CAL Licenses

V1.0 CIS - Performance Cloud Team Document | Client Facing Instructions



Table of Contents

Find the RD License Server ID	3
Install the RDS CAL Licenses	4

Find the RD License Server ID

- 1) Connect to the server that contains the RD Licensing Manager role as an administrator.
 - a. Make sure that this server also has an internet connection, as the RD Licensing Manager will need it to activate the CAL licenses.
 - b. Make sure that your Licensing Server is activated. You should see **Activated** in the RD Licensing Manager panel.
- 2) Right click your server listed in the **RD Licensing Manager** and select **Properties** from the contextual menu.

😪 RD Licensing Manager					
Action View Help					
All servers	me	Activation Status	D	iscovery Scope	Configuration
-	ADDC	Refresh	-	omain	ОК
		Review Configuration			
		Install Licenses			
		Activate Server			
		Advanced	>		
		Create Report	>		
		Delete Reports			
		Manage Licenses			
		Properties N			
		<u>*5</u>			

- In the first tab, Connection Method, make sure to select Web Browser from the list menu, located next to the Connection Method option.
- 4) At the bottom of the same window, you will see an option called **License Server ID** with a value to its right, which looks like an activation key. Copy that value and send it to us.

Connection Method	Doguino d Infor	antian Ontianal Information	~				
Connection Method	Nequired inion						
Connection met	thod:	Automatic connection (recommended)					
Description:	1	Automatic connection (recommended) Web Browser Telephone					
Requirements:		Microsoft Clearinghouse over the Internet. The computer must be able to connect to the Internet by using a Secure Sockets Layer (SSL) connection.					
Select Country	or Region:						
Product ID:		00376-50000-49878-AT753					
License Server	ID:	F64FY-	FH6V				
		ОК	Cancel				

5) Make sure to click on **Ok** to close out of that window and save the **Connection method** that you have changed at step 3.

Install the RDS CAL Licenses

- 1) Connect to the server that contains the RD Licensing Manager role as an administrator.
 - a. Make sure that this server also has an internet connection, as the RD Licensing Manager will need it to activate the CAL licenses.
 - b. Make sure that your Licensing Server is activated. You should see **Activated** in the RD Licensing Manager panel.
- 2) Right click your server listed in the **RD Licensing Manager** and select **Install Licenses** from the contextual menu.



3) Enter the activation key provided by Sherweb in the box, and then click Next.

Install Licenses	Wizard						×
Obtain Clie Provide t	nt License the client licer	Key Pack ise key pack	ID.				9
To install Web Site	your licenses, located at:	, you must ob	tain <mark>a license</mark>	key pack I) from the Re	mote Desktop	Licensing
		https://ac	tivate.micros	oft.com			
To obtain your licen License).	n a <mark>li</mark> cense key nse program (fi	v pack ID, you prexample, re	u will need th stail product p	e license co backaging, E	de informatior interprise Agr	n that you rece eement, or Sel	ived from ect
You will a	also need your	license serve	er ID. Your lic	ense server	ID is:		
		F64FY		and the second second	-XFH	6V	
After you type the I	have obtaine ID in the follow	d the license ving boxes.	key pack ID	from the Rer	note Desktop		eb Site,
V2HIV				Contraction of the local distribution of the			
	Please write o with the Micro	down this ID. osoft Clearing	Having this i house, shoul	nformation w d you need a	th you will fa assistance wit	cilitate commur th recovering li	nications censes.
				<	<u>B</u> ack	<u>N</u> ext >	Cancel

- 4) Click on **Finish** on the second screen.
- 5) You will now see the RDS CAL licenses listed inside of the RD Licensing Manager and there are no further steps to take.





© Sherweb Inc. Confidential

